

General information about the[.]

10/15/2026 11:50:17

FAQ Article Print

Category:	FAQ in English::KOMPAS-3D FAQ	Last update:	10/24/2024 15:09:11
State:	public (all)		

Keywords

Guardant лицензия ключ

Problem (public)

General information about the Guardant SLK licensing system (hereinafter referred to as Guardant)

Solution (public)

KOMPAS-3D, starting from version v22, and the ASCON SOLUTION PACKAGE, starting from version 22.3, use the Guardant licensing system from the AKTIVE company. (The ability to work with Sentinel HASP for these versions will be retained) Licenses are placed on software and hardware keys.

1. Guardant keys (license media)
 - 1.1 Guardant DL Software Key
 - 1.2 The Guardant Sign Hardware Key
2. License Manager of the Guardant Control Center

1. Guardant keys (license media)
For the Guardant DL software key and the Guardant Sign hardware key to work locally (the key is located on the same PC where the protected application is running), the installation of a license manager is not required (including for temporary trial licenses). Information on updating licenses on Guardant keys is provided in the article #FAQ7001433
1.1 Guardant DL Software Key
1.1 The Guardant DL software Key
A key without a physical medium that is linked to the hardware characteristics of the computer. The placement of the Guardant DL key is possible on Windows, Linux and macOS operating systems.
Activation of the Guardant DL software key is described in article #FAQ7001432. It can include all types of licenses at the same time (local/network temporary/permanent).

The Guardant DL software key works in virtual machines (VMs), but at the same time, the license for this key itself may have a restriction on use in a VM (The KOMPAS-3D trial license does not work in a VM)

1.2 The Guardant Sign hardware key

The hardware key is not linked to the hardware parameters in any way and can be physically transferred to another computer without any additional manipulations. license information is stored in the permanent non-volatile memory of the hardware key.
The hardware key can be transferred to another computer or to a virtual machine.

The hardware key is not tied to the hardware parameters in any way and can be physically transferred to another computer without any additional manipulations. License information is stored in the permanent non-volatile memory of the hardware key.
The hardware key can be transferred to another computer or to a virtual machine.

2. License Manager of the Guardant Control Center
To transfer network licenses to workstations on the local network, the Guardant Control Center (hereinafter referred to as GCC) must be installed on the license server
Installing the GCC License Manager on workstations that use network licenses is not required.

For instructions on installing GCC, see article #FAQ7001411

The work with the license manager is carried out through the web interface <http://localhost:3189> in the browser.

Contact information of the developer of the Guardant licensing system
The Asset Company
Moscow, st. Ball bearings, building 1, 4th floor
Progress Plaza Business Center
+7 (495) 925-77-90 ext. 309
[1]www.guardant.ru

[1] <http://www.guardant.ru/>